# 

# QUICK START GUIDE Automate™ Crestron

INTEGRATION SUPPORT



#### AUTOMATE PULSE HUB PRO OVERVIEW

Elevate your Automate experience by seamlessly integrating Automate motorized shades into CRESTRON SYSTEM. The Automate Pulse PRO Hub offers a powerful integration with discrete shade control and two-way communication, providing real-time updates on shade position and battery levels. Featuring both Ethernet (CAT 5) and 2.4GHz wireless connectivity, the Pulse PRO Hub ensures smooth home automation integration through an easy-to-access RJ45 port located on the back of the hub. Each hub supports up to 30 shades, making it a versatile solution for any home automation setup.

#### **GETTING STARTED:**

In order to integrate your motorized window treatments with Crestron, you will need to have:

- Downloaded the free Automate Shades App via the Apple App Store (available under iPhone /iPad apps) or the Google Play Store.
- Purchased one or more Automate Pulse PRO depending on size of the space and additional repeaters if is required.
- Integrated your motorized window treatments onto Automate Shades App.

#### INSTRUCTIONS INCLUDED:


- Set up instructions for both the Automate Shades App & Automate Pulse Hub PRO.
- Crestron Driver Installation Instructions
- Crestron Driver Guide
- Integration Diagram
- Integration FAQ's





#### **CRESTRON HUB DRIVER INSTALLATION SECTION:**

- 1. Find Rollease Acmeda ARC2 module in the Crestron Application Marketplace.
- 2. Unzip folder and open the Rollease Acmeda ARC2 v1.0 Demo IP CP3.smw file in SIMPL Windows.



- 3. Locate the Rollease Acmeda ARC2 v1.0 Command Processor IP symbol in the SIMPL Windows program and replace the current IP address on the Pulse\_Hub\_IP\_Address parameter with the actual IP address of your hub.
- 4. Comment out the entire "Motors" subfolder in the example program.
- 5. Compile and load the example program to your Crestron processor.
- 6. Open the Rollease Acmeda ARC2 v1.0 Demo XPanel.c3p file to open the XPanel simulator on your computer (you may need to install Adobe Air first with the included CrestronXPanel installer files).
- 7. Once the XPanel opens, click Options 🗆 Host Settings in the top menu and enter the IP address of your Crestron processor in the Hostname/IP Address field and hit connect. This will connect your XPanel to your processor and allow for using the XPanel as a simulator in place of a physical touchpanel.
- 8. The module will automatically attempt to communicate with the hub when the program loads. Once communication is established with the hub, the Communicating indicator on the top right of the XPanel will illuminate. If it does, proceed to the next steps. If it does not, verify the IP address you entered in SIMPL Windows is correct and that the hub and Crestron processor are on the same network.
- 9. On the Command Processor tab in the XPanel, click the "Setup" button so it illuminates blue.
- 10. Using a remote or the Rollease Acmeda app, move each shade to initiate a response (in order to identify each).
- 11. The address of the last motor that moved/responded will automatically populate in the Motor Address field on the XPanel. Move each motor to identify each address.





STEP 2:

C ROLLEASE	HUB NAME My House HUB MAC ADDRESS 24:0a:c4:27:73:34 COMMAND PROCESSOR	COMMUNICATING INITIALIZED
INITIALIZE	DEBUG	SETUP
MOTOR ADDRESS		
	91D	
	COMMAND PROCESSOR MOTOR CONTROL	

- 12. Once you have the address for all your desired motors, uncomment the entire "Motors" subfolder in the example program and enter in the appropriate address in the Motor\_Address parameter for each instance of the Rollease Acmeda ARC2 v1.0 Motor Control module in your program (the example program has 5 motors. You may have more or less in your installation). Once the addresses have been entered, recompile and reload your program.
- 13. Refer to the help files included in the module package for further details and information regarding the capabilities of the module(s).

STEP 3: CRESTRON **Certified Module** Partner: Rollease Acmeda CERTIFIED CRESTRON Model: ARC2 Hub **Device Type: Shade/Motor Control** Integrated Partner **GENERAL INFORMATION** SIMPLWINDOWS NAME: Rollease Acmeda ARC2 v1.0 Motor Control CATEGORY: Shades/Drapes VERSION: 1.0 SUMMARY: This module controls all the Rollease Acmeda ARC2 motor control points. This is a standalone "component" module allowing for controlling a single motor. This module requires an instance of the primary "Rollease Acmeda ARC2 v1.0 Command Processor IP" communication module be included in the program. Control for this GENERAL NOTES: "component" module will be bound to and flow through the primary Comm module.






rolleaseacmeda.com © 2019 Rollease Acmeda Group

#### **Common Mistakes:**

• Entering the wrong IP address in the "IP Address" configuration line. If you're failing to discover devices double check this!

### CRESTRON SMART HOME CONTROL SYSTEM CONNECTION:



1. Gross 6. Grange 5. Million Drunger 7. Million 4. Brans 6. Brans 2. Drakp 3. A/Ima S. Giner

AS SOCKET





## FREQUENTLY ASKED QUESTIONS:

#### Q. No Pulse Hub PRO detected.

A. Make sure that your Automate Pulse PRO is connected to the correct network and get an IP Address available and still communicating with the network using the Automate Shades App.

#### Q. Shade limits are not set properly.

A. Calibrate shade limits with your Rollease Acmeda remote before setting the appropriate open and close time within CRESTRON SYSTEM.

#### Q. Shade is not moving at all.

A. Make sure the selected Pulse Hub PRO is the correct Pulse Hub PRO for the shade to be controlled. Confirm the correct bindings are set in the CRESTRON System connections tab between the Pulse Hub PRO and Shade drivers.

#### Q. I have multiple Pulse PRO Hubs, what do I do?

A. Load two Automate Pulse Hub PRO drivers. After selecting "Retrieve Hubs" located in the driver actions tab, you will see different Automate Pulse Hubs PRO - select the desired one.

#### Q. I don't see any shade bindings in the Pulse Hub PRO driver?

A. Select "Retrieve Shades" located in the driver actions tab.

#### Q. How do I scan for available Automate Pulse PRO Hubs?

A. Once the Automate Pulse Hub PRO is properly connected via the Ethernet cable or Wireless network, navigate to the Automate Pulse Hub Properties page within Composer. Select "Retrieve Hubs" located in the driver actions tab.

#### Q. We get unexpected responses from the CRESTRON system, or "?" symbols

A. Ensure that all connections using the ethernet port or Wi-Fi are working properly. The missed connection has been known to yield unwanted or unexpected results.

#### SUPPORT RESOUCES:

For further assistance, contact your retailer, visit our website at <u>www.rolleaseacmeda.com</u>.



